


# Sequence Library

**Sequence Library** shows a list of all sequences in the scene.



## Sequence Preview


To preview a sequence without converting it into animation, the user can highlight the animation icon part of the sequence, which will be converted into a play icon, clicking the play icon will preview the sequence, as shown in the following image



On the left side of the Sequence library the user can do the following:

**Find affected Objects:** zooms the view in the 3D area to the objects affected by this sequence, which makes it easy to find what objects the sequence affects in the scene.

**Apply Sequence to Animation Time Line:** adds the contents of the sequence to the animation timeline, this can also be achieved by dragging the animation and dropping it on the 3D Area



When applying Sequence to **Animation Time Line** the following dialog appears allowing the user to repeat the sequence multiple times. or to use it in a follow-path animation.

Sequences will be added starting from the **current frame** in the **Animation Timeline**

**Attach Sequence with Object:** This option attaches the selected unattached sequence to the selected object to affect it, better explained in the following tutorial

**Make Flex Object Stationary:** in case you have a sequence moving **VR Guide** legs, and at the same time moving it from the place, you can use this option to remove the move from place part from the sequence and make the **VR Guide move in place**, this is very useful to apply user desired motion on the **VR Guide**

**Delete Selected Sequence:** Deletes the currently selected sequence


**Delete All Sequences:** Deletes all sequences in the Sequence Library

The following tutorial shows how to use **Sequence Library** to add **VR Guide** to the VR experience


[https://www.youtube.com/embed/lufG\\_FcilC8](https://www.youtube.com/embed/lufG_FcilC8)

## Sequence Groups

Sequences in **Sequence Library** can be organized in groups, a new group can be added by clicking on the + button next to group tabs, to rename **Sequence Group** the user needs to double-click on its tab label as shown below



When deleting a sequence group the user will get the option to delete sequences in the group or to move them to the Default sequence group, as shown in the following image.



---

Revision #2

Created 4 September 2022 07:01:43 by Ashraf Sultan

Updated 8 December 2022 06:56:26 by Jamal Said